




**TRIBOMAR**®  
onboard fluid management

**Tribomar USB  
Connect Software**



**TRIBOMAR**®

**USB Connect with  
TriboLab<sup>3</sup> device**












Connect the device with an  
USB-C cable to the PC  
(Connector on the back)



To transfer the data from your TriboLab<sup>3</sup> device to PC, please install Tribomar Software from enclosed USB-Stick







Tribomar Software Window starts with connected TriboLab device

Tribomar - connected - Version 1.80.0.0

Tribolab

Device Date/Time: 13 December 2023 15:53

COM-Port: COM12-Silicon Labs CP210x USB to UART Brid

Num Records: 43

NumLocations: 15

Set actual date and time

Export data to PC

MeasurementResults:

ID	Location	Test Version	Method	Type	Results	Time and Date
0	Cylinder 1	0	1	BP/Castrol Cyltech	697	09/01/2000 00:09:49
1	Cylinder 1	0	1	BP/Castrol TLX Plus	152	09/01/2000 00:37:12
2	Cylinder 1	0	1	BP/Castrol TLX Plus	210	09/01/2000 00:42:04
3	Cylinder 1	0	1	BP/Castrol TLX Plus	319	09/01/2000 00:42:15
4	Cylinder 1	0	1	BP/Castrol TLX Plus	411	09/01/2000 00:42:25
5	Cylinder 1	0	1	BP/Castrol TLX Plus	590	09/01/2000 00:42:35

stored data

Loading data

Save data

Save As

Documents >

File name: tribomar-2023.12.13-13.58.11

Save as type: Excel Workbook (\*.xlsx)

Confirm

File saved. Do you want to delete all measures?


Choice to delete all data or not

## Troubleshooting

If COM Port does not show a device and loading bar stops @ 50% then check your **anti virus protection**





If still no progress then check Windows Device Manager for Ports (COM & LPT) / Silicon Labs CP210x must be shown



## Troubleshooting

Install Silicon Labs CP210x if error occurs  
(message – device is not working properly)  
from USB Drive



If requested  
restart your PC



**TRIBOMAR**®  
onboard fluid management

Biedenkamp 3e  
D-21509 Glinde/Hamburg  
Germany  
Tel: +49 40 7309 1399 0  
Email: [info@tribomar.com](mailto:info@tribomar.com)